KnittingFairy

Reusable Cup Cozies



Four row yarn over buttonhole

Size 8 needles
Worsted weight yarn

Loosely cast on 35 sts.
Row 1: P1, (K1, P1) Rep across.
Row 2: K1, (P1, K1) Rep across.
Row 3: P1, (K1, P1) Rep across.
Row 4: K1, M1R, Knit to last st, M1L, K1.
Row 5: Purl.
Row 6: Knit.
Row 7: Purl.
Repeat rows 4-7 5 times more. (47 sts total)
Row 28: P1, (K1, P1) rep across.
Row 29: K1, (P1, K1) Rep across.
Row 30: P1, (K1, P1) rep across.
Row 31: K1, (P1, K1) Rep across.
Row 32: P1, (K1, P1) rep across.
Bind off loosely in rib. Do not weave in ends.



Button band: with the with right side facing, along left edge, start with the Japanese button band trick, then pick up and knit 26 sts, then repeat the Japanese button band trick. (28 sts total)
Row 1: (WS) P3, (K2, P2) across, end P1.
Row 2: K3, (K2, P2) across, end K1.
Repeat rows 1 and 2. Twice and then row 1 once more.
Bind off in rib. Remove slipknots, weave in ends.

Button hole band:
with the with right side facing, along right edge, start with the Japanese button band trick, then pick up and knit 26 sts, then repeat the Japanese button band trick. (28 sts total)
Row 1: (WS) P3, (K2, P2) across, end P1.
Row 2: K3, (P2, K2) rep to end, K1.
Row 3: P3, K2, P1. Turn
K1, P2, K3. Turn.
P3, K2, P1, yarn over, P1, (K2, P2) three times, K2, P1. Turn.
K1, P2, (K2, P2) three times, K1. Turn.
P1, (K2, P2) three times, K2, P1, YO, P1, K2, P3. Turn.
K3, P2, K1. Turn.
P1, K2, P3.

Row 4: K3, P2, *K1, K together next st and yarn over, work to one stitch before next yarn over, repeat from *, working to end.
Row 5: P3, (K2, P2) across, end P1.
Bind off in rib. Remove slipknots, weave in ends. Note that the buttonhole side has 2 fewer “rows” than the buttonband side- this is due to the turning that occurs between the holes. These short rows add two rows to the overall total.

Copyright 2017, Knitting Fairy®